


คู่มือการเพิ่ม Account ใหม่


Microsoft Outlook 2013 [POP3]

เปิดโปรแกรม Microsoft Outlook

หมายเหตุ โปรแกรม Microsoft Outlook สามารถเพิ่ม Account E-mail ได้มากกว่า 1 Account



คลิกเลือก **File >> Add Account**



ติ๊กเลือก **Manually configure server settings or additional server types**

จากนั้นกด Next

The screenshot shows the 'Add New Account' dialog box with the 'Auto Account Setup' section selected. The 'Auto Account Setup' section is titled 'Auto Account Setup' and includes the instruction 'Connect to other server types.' Below this, there are three radio button options: 'E-mail Account', 'Text Messaging (SMS)', and 'Manually configure server settings or additional server types'. The 'Manually configure server settings or additional server types' option is selected. Below the radio buttons, there are four input fields: 'Your Name' (with an example 'Ellen Adams'), 'E-mail Address' (with an example 'ellen@contoso.com'), 'Password', and 'Retype Password' (with the instruction 'Type the password your Internet service provider has given you.'). At the bottom right, there are three buttons: '< Back', 'Next >', and 'Cancel'. The 'Next >' button is highlighted with a blue border.


ติ๊กเลือก **Internet E-mail** และกด Next

The screenshot shows the 'Add New Account' dialog box with the 'Choose Service' section selected. The 'Choose Service' section is titled 'Choose Service' and includes four radio button options: 'Internet E-mail', 'Microsoft Exchange or compatible service', 'Text Messaging (SMS)', and 'Other'. The 'Internet E-mail' option is selected. Below the radio buttons, there are four descriptions: 'Connect to POP or IMAP server to send and receive e-mail messages.', 'Connect and access e-mail messages, calendar, contacts, faxes and voice mail messages.', 'Connect to a mobile messaging service.', and 'Connect to a server type shown below.' Below the 'Other' description, there is a text box containing 'Microsoft Outlook Hotmail Connector'. At the bottom right, there are three buttons: '< Back', 'Next >', and 'Cancel'. The 'Next >' button is highlighted with a blue border.

หน้าต่าง Change Account

Type	Meaning	Example
You name	ชื่อ Account	example@abcd.com
E-mail address	ชื่อ Account	example@abcd.com
Incomming mail server	mail.[โดเมนของลูกค้า]	mail.abcd.com
Outgoing mail server	mail.[โดเมนของลูกค้า]	mail.abcd.com
User Name	ชื่อ Account	example@abcd.com
Password	รหัสผ่าน	xxxxxxxxxxxxxxxx

Change Account
✕



Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information

Your Name:

E-mail Address:

Server Information

Account Type:

Incoming mail server:

Outgoing mail server (SMTP):

Logon Information

User Name:

Password:

Remember password

Require logon using Secure Password Authentication (SPA)

Test Account Settings


After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings by clicking the Next button

หน้าต่าง More Setting

คลิกเลือก **More Setting**

ป้าย **Outgoing server** ตั้งค่าตามรูป



The image shows a screenshot of the 'Internet E-mail Settings' dialog box, specifically the 'Outgoing Server' tab. The dialog has a title bar with a close button (X) and four tabs: 'General', 'Outgoing Server', 'Connection', and 'Advanced'. The 'Outgoing Server' tab is selected. The settings are as follows:

- My outgoing server (SMTP) requires authentication
 - Use same settings as my incoming mail server
 - Log on using
 - User Name:
 - Password:
 - Remember password
 - Require Secure Password Authentication (SPA)
- Log on to incoming mail server before sending mail

At the bottom right, there are two buttons: 'OK' and 'Cancel'.

ในส่วนของป้าย Advance

Leave a copy of messages on server คือ กำหนดให้มีการลบเมลที่เก็บไว้บน Server

หมายเหตุ หากไม่ติ๊กเลือกเอาไว้ Outlook รับเมลเข้ามายังตัวโปรแกรม จะลบเมลจาก Server ทันทีที่เปิดโปรแกรมไว้

Remove from server after คือ กำหนดวันลบเมลที่เก็บไว้บน Server

หมายเหตุ หากใช้ รับ-ส่ง เมลล์ หลายๆเครื่อง รวมทั้งมือถือด้วย ควรกำหนดวันให้เหมาะสม เพราะเมื่อเครื่องใดเครื่องหนึ่งทำการรับเมลล์ และลบเมลล์ออกจาก Server ไปแล้ว เครื่องอื่นๆ ก็ไม่สามารถที่จะไปดึงเมลล์จาก Server ได้

จากนั้นคลิก **OK** รอจนกว่าระบบจะทดสอบเสร็จสมบูรณ์... และคลิก **Finish**

